




Materials List



STANDARD SIZE PILLOW -makes two

(pillow size approx. 20" x 26") ... Finished Size- 20 1/2" x 30"

- * One and a half yard of (42"-44" wide) fabric for the body of the pillow cover
- One half yard of complimentary fabric for the "finished edge"
- * Matching thread

QUEEN SIZE PILLOW -makes two

(pillow size approx. 20" x 30") ... Finished Size- 20 1/2" x 34"

- * One and three fourths yard of (42"-44" wide) fabric for the body of the pillow cover
- * One half yard of complimentary fabric for the "finished edge"
- * Matching thread

KING SIZE PILLOW -makes two


(pillow size approx. 20" x 36") ... Finished Size- 20 1/2" x 40"

- * Two and one eighth yards of (42"-44" wide) fabric for the body of the pillow cover
- * One half yard of complimentary fabric for the "finished edge"
- * Matching thread


INSTRUCTIONS

page 1

- Body of pillow—square fabric ends and cut into two equal lengths approx. 27" long by "width of fabric"
- Edge of pillow—square fabric ends and cut into two equal lengths approx. 9" wide by "width of fabric"



Body of Pillow Cover




Edge


12"
Two 9" x 42" strips
↩

- Roll body of pillow starting at the long (42"-44") edge...leaving a few inches unrolled at end.
- With right side together, wrap the 9" strip of "edge" fabric around the rolled body of pillow cover.

• Pin all three layers together.




• Sew along pinned edge 1/4" from raw edge...removing pins as you sew.




• Reach in and grab the rolled body of the pillow cover...pulling it out of the looped "edge."

• Press flat with seam allowance toward the "finished edge."



*Fold in half (wrong sides together) aligning "finished edge" and press again.




For STANDARD SIZE PILLOW—Trim raw edges so folded pillow cover measures
30 1/2" by 21 1/2"

(*NOTE: For other sizes...trim raw edges of folded pillow cover 1/2" larger than finished size.)

Sew both unfinished seams (long "side seam" first) following the "French Seam Directions" below:


"French Seam Directions"

Step #1—With wrong sides together...sew 1/4" from raw edge...trim to "slight" 1/8" seam allowance.



Step #2—Turn inside out and press along seam line.

Step #3—With right sides together sew approx. 1/4" from previously sewn seam (to "encase" raw edge.)



Step #4—Turn right side out and press along seam line.